

Mini Bulletin XR15AS  
 ConnectKey 1.5 R15-08  
 WorkCentre3655/58xx/59xx/6655/  
 72xx/78xx/7970  
 Release 073.xxx.035.24100

Release Date: October 30, 2015



Version 1.0

## Purpose

This Bulletin is intended ONLY for the specific security problem identified below. The problem identified has been rated a criticality level of **IMPORTANT**

Includes fixes for:

- Logjam Vulnerability In OpenSSL (CVE-2015-0400). A vulnerability in TLS protocol versions 1.2 and earlier allows man-in-the-middle attacks to occur against vulnerable systems that support older key exchange methods. Xerox has included a non-vulnerable version of OpenSSL in the software version available below.
- Includes fixes for Security HP WebInspect scan failures such as Cross Site Scripting vulnerabilities found in this SPAR release.

## Software Release Details

**If your software is higher or equal to the versions listed below no action is needed.**

**Otherwise, please review this bulletin and consider installation of this version.**

Model	WorkCentre 3655	WorkCentre 58xx <sup>1</sup>	WorkCentre 5945/5955	WorkCentre 6655
System SW version	073.060.035.24100	073.190.035.24100	073.091.035.24100	073.110.035.24100
Network Controller version	073.065.24100	073.195.24100	073.095.24100	073.205.24100
Link to SW update and Install Instr.	<a href="#">Available here</a>	<a href="#">Available here</a>	<a href="#">Available here</a>	<a href="#">Available here</a>

<sup>1</sup> WorkCentre 5845/5855/5865/5875/5890

Model	WorkCentre 7220/7225	WorkCentre 7830/7835	WorkCentre 7845/7855	WorkCentre 7970
System SW version	073.030.035.24100	073.010.035.24100	073.040.035.24100	073.200.035.24100
Network Controller version	073.035.24100	073.015.24100	073.045.24100	073.205.24100
Link to SW update and Install Inst.	<a href="#">Available here</a>	<a href="#">Available here</a>	<a href="#">Available here</a>	<a href="#">Available here</a>

Save the file to a convenient location on your workstation. Unzip the file if necessary.

**Note:** For the WorkCentre 3655 & WorkCentre 6655 Only: Once the system is upgraded to this SPAR release it cannot be downgraded to GM release 072.060.034.16800 / 072.111.044.20500, respectively, or SPAR release 072.060.134.32804 / 072.110.134.32804, respectively.